# **User Manual**

## **Common Tasks**

## View PRE or POST wafer profiles

- 1. Upload a PRE or POST .sbw file.
- 2. Select Thickness or Flatness from the dropdown menu.
- 3. Select **PRE** or **POST** in the segmented control.
- 4. Select one or more **Slots** from the multiselect dropdown menu. If multiple slots are selected, the plots are displayed in order.
- 5. (Optional) Check Mask notch in the sidebar to mask notch and filter out outlier values.
- 6. Click Plot.

### View REMOVAL wafer profile

- 1. Upload both PRE and POST .sbw files.
- 2. Select Thickness or Flatness from the dropdown menu.
- 3. Select **REMOVAL** in the segmented control.
- 4. Select PRE slots and POST slots. If counts differ, the slots are paired in order.
- 5. (Optional) Check Overlay line charts in the sidebar to show PRE/POST on top of REMOVAL line charts.
- 6. Click Plot.

### View average wafer profiles

- 1. Check Average Profile.
- 2. In PRE/POST profile mode: plots the average radial profile for the selected profile mode.
- 3. In REMOVAL profile mode: plots the average removal profile.

## **User Interface**

## **Top controls**

- Upload PRE .sbw | Upload POST .sbw: load .sbw files.
- Thickness | Flatness | dropdown menu: select graph mode.
- PRE | POST | REMOVAL | segmented control: select profile mode.
- Average Profile checkbox: switch to average profile mode.

#### Sidebar — Display controls

- Color clip low (%): slide to set the lowest percentile used for color range to reduce the effect of a notch (outlier values) skewing colors (default 0.5).
- Color clip high (%): slide to set the highest percentile used for color range (default 100).
- Mask notch: replaces notch (outlier values) (beyond  $k \times MAD$ , default k = 4) with NaN to prevent notch from skewing colors.
- (REMOVAL only) Overlay line charts: overlays PRE/POST lines on removal line plots.

#### Angle selection

• Angle slider: slide to select an angle for a single-angle line chart.

The angle and direction at which the wafer has been line-scanned is indicated by the arrow shown on the icon of a wafer on the top right of the chart.

#### **Controls and interactions**

- Hover: shows x/y/z values.
- Pan/Zoom: use mouse to drag/scroll in plots.
- Turnable rotation: use mouse to drag and turn the surfaces.
- (REMOVAL only) \[ \sum / \left| button: to switch between 2D and 3D plots for PRE and POST.

# **Code Explanation**

# **Utility Functions**

#### reset\_plot()

A reset switch to control session state.

```
def reset_plot(flag_key: str):
st.session_state[flag_key] = False
```

Streamlit reruns when the user interacts with the application (e.g., selecting new slots). st.session\_state[flag\_key] = False ensures that plotting is initiated by the **Plot** button.

The function is used in st.multiselect, for example:

```
...
plot_key = f"do_plot_{profile_mode}"
sel = st.multiselect("Slots", labels, default=None, key=f"{profile_mode}_slots",
on_change=reset_plot, args=(plot_key,))
```

Changing slot options resets session state, requiring the **Plot** button to be clicked again. on\_change=reset\_plot invokes reset\_plot() to be run whenever the widget's value (slots in this case) is changed. arg=(plot\_key,) then passes plot\_key=f"do\_plot\_{profile\_mode}" as the argument to reset\_plot(). As a result, when the widget's value is changed, st.session\_state[plot\_key]=False.

```
if st.button("Plot", key=f"plot_btn_{profile_mode}"):
    st.session_state[plot_key] = True
...

if st.session_state.get(plot_key, False):
    if not sel_keys:
        st.warning("Choose at least one slot.")
    else:
        if avg_profiles:
```

Then, the code above checks if st.session\_state[plot\_key] is True. Plotting is initiated only when the user has selected slots and clicked the **Plot** button.

#### average\_profile()

Compute average radial profile by combining both + r and - r sides.

```
def average_profile(Z_line: np.ndarray) → np.ndarray:
    Z_line = np.asarray(Z_line, dtype=float)
if Z_line.size == 0:
    return np.array([])
Z_full = np.vstack([Z_line, Z_line[:, ::-1]])
```

```
with np.errstate(all='ignore'):
return np.nanmean(Z_full, axis=0)
```

Z\_full = np.vstack([Z\_line, Z\_line[:, ::-1]]) stacks the original (+ r) array and the mirrored (- r) array vertically (::-1 reverses the sequence). Then, the function returns the average of the stacked arrays. (np.errstate(all='ignore') suppresses warning messages.)

## SBW File Parsing and Cleaning

#### parsecleansbw()

Parse (using parsesbw()) and clean (using cleansbw()) the sbw file uploaded by the user, and return it in a cleaned dict format.

```
def parsecleansbw(uploaded_bytes: bytes) → Dict[str, Any]:
    import tempfile
    obj = None
    with tempfile.NamedTemporaryFile(delete=False, suffix=".sbw") as tmp:
        tmp.write(uploaded_bytes)
        tmp_path = tmp.name
    try:
        obj = parsesbw(tmp_path)
        return cleansbw(obj)
finally:
    try:
        os.unlink(tmp_path)
    except Exception:
        pass
```

- parsesbw() parses the raw .sbw file (using a file path) and returns an sbwinfo object.
- cleansbw() takes an sbwinfo object and converts it into a clean dictionary.
- parsecleansbw() bridges these two functions: it takes the raw file bytes uploaded by the user, writes them into a temporary sbw file on disk, so that it can use parsesbw() to parse that file and use cleansbw() to convert it into a clean dictionary, which is the final output of this function. In essence, this function returns the output of cleansbw(), and its input is the uploaded file bytes instead of a file path.

## **Wafer Matrix & Slot Caching**

#### Thkmatrix() & Flatmatrix()

Build a 2D thickness/flatness matrix with rows = Angle and columns = Radius.

```
def Thkmatrix(wafer):
    r = np.asarray(wafer.get('Radius', []), dtype=float)
    theta = np.asarray(wafer.get('Angle', []), dtype=float)
    profiles = wafer.get('Profiles', [])
    nt, nr = len(theta), len(r)
    Thk = np.full((nt, nr), np.nan, dtype=float)
    for i in range(nt):
        line = np.asarray(profiles[i], dtype=float) if i < len(profiles) else np.array([], dtype=float)
        if line.ndim == 2 and line.shape[1] > 0:
            Thk[i, :min(nr, line.shape[0])] = line[:nr, 0]
        else:
            Thk[i, :min(nr, line.size)] = line.ravel()[:nr]
    return r, theta, Thk

def Flatmatrix(wafer):
    r = np.asarray(wafer.get('Radius', []), dtype=float)
```

```
theta = np.asarray(wafer.get('Angle', []), dtype=float)
profiles = wafer.get('Profiles', [])
nt, nr = len(theta), len(r)
Flat = np.full((nt, nr), np.nan, dtype=float)
for i in range(nt):
    line = np.asarray(profiles[i], dtype=float) if i < len(profiles) else np.array([], dtype=float)
    if line.ndim == 2 and line.shape[1] > 1:
        Flat[i, :min(nr, line.shape[0])] = line[:nr, 1]
    else:
        Flat[i, :min(nr, line.size)] = line.ravel()[:nr]
return r, theta, Flat
```

This function loops over every angle i and retrieves the corresponding Thk (Flat ) data at every r. Thkmatrix() (Flatmatrix()) takes Thk (Flat ) data from the first (second) column of line, a 2D array representing one scan line.

#### build\_SlotCache()

Take wafer\_dict and build SlotCache.

```
def build_SlotCache(wafer_dict) → SlotCache:
  r, theta, Thk = Thkmatrix(wafer_dict)
  _, _, Flat = Flatmatrix(wafer_dict)
  Rmax = finite_max(r, 0.0)
  if theta.size and r.size:
    theta_full = (np.concatenate([theta, theta + np.pi]) % (2*np.pi))
    Thk_full = np.vstack([Thk, Thk[:, ::-1]]) if Thk.size else np.empty((0, 0))
    Flat_full = np.vstack([Flat, Flat[:, ::-1]]) if Flat.size else np.empty((0, 0))
    T, Rm = np.meshgrid(theta_full, r, indexing='ij')
    X_{mir} = Rm*np.cos(T)
    Y_mir = Rm*np.sin(T)
  else:
    Thk_full = np.empty((0, 0))
    Flat_full = np.empty((0, 0))
    X_{mir} = np.empty((0, 0))
    Y_mir = np.empty((0, 0))
  return SlotCache(
    r=r, theta=theta, Thk=Thk, Flat=Flat,
    Rmax=Rmax, X_mir=X_mir, Y_mir=Y_mir, Thk_mir=Thk_full, Flat_mir=Flat_full)
```

This function uses the following polar-coordinate identity:

$$(r, heta)\equiv (-r, heta+\pi)$$

theta\_full = (np.concatenate([theta, theta + np.pi]) % (2\*np.pi)) extends theta by mirroring it across the wafer theta + np.pi while % (2\*np.pi) ensures that angles stay in the range  $[0, 2\pi)$ . Then, Thk\_full = np.vstack([Thk, Thk[:, ::-1]]) if Thk.size stacks the original (+ r) array and the mirrored (- r) array vertically (::-1 reverses the sequence). This way, the mirrored rows are stacked under the original rows to form a full  $0 - 360^{\circ}$  matrix.

## **Plot Utilities**

#### robust\_clip()

Clip values based on plo (lowest percentile) and phi (highest percentile) to reduce the effect of a notch (outlier values) skewing colors.

```
def robust_clip(Z: np.ndarray, p_lo: float, p_hi: float):
    Zf = Z[np.isfinite(Z)]
    if Zf.size == 0:
        return Z, 0.0, 1.0
    vmin = float(np.nanpercentile(Zf, p_lo))
```

User Manual

4

```
vmax = float(np.nanpercentile(Zf, p_hi))
if not np.isfinite(vmin): vmin = 0.0
if not np.isfinite(vmax): vmax = vmin + 1.0
if vmin >= vmax:
    vmax = vmin + 1e-9
return np.clip(Z, vmin, vmax), vmin, vmax
```

The function limits the input array z to values within the range ( vmin, vmax).  $vmin = float(np.nanpercentile(Zf, p_lo))$  and  $vmax = float(np.nanpercentile(Zf, p_hi))$  computes the lowest percentile and the highest percentile of the data, respectively, from vmax = vmax, both of which are set by the user through color clip sliders ( vmin, vmax).  $vmin = float(np.nanpercentile(Zf, p_lo))$  and vmax = vmax

```
with st.sidebar:
st.markdown("**Display controls**")
p_lo = st.slider("Color clip low (%)", 0.0, 5.0, 0.5, 0.5)
p_hi = st.slider("Color clip high (%)", 95.0, 100.0, 100.0, 1.0)
if p_hi <= p_lo:
    p_hi = min(100.0, p_lo + 0.5)
```

By default, plo is set to 0.5 and phi is set to 100—only values below the 0.5th percentile are clipped.

#### masknotch()

Mask notch (outlier values) in the array using Median Absolute Deviation (MAD).

```
def masknotch(Z: np.ndarray, k: float=4):
    Zm = np.asarray(Z, dtype=float).copy()
    m = np.isfinite(Zm)
    if not m.any():
        return Zm
    Zf = Zm[m]
    med = float(np.nanmedian(Zf))
    mad = float(np.nanmedian(np.abs(Zf - med))) * 1.4826
    if mad == 0 or not np.isfinite(mad):
        return Zm
    out = np.abs(Zm - med) > (k * mad)
    Zm[out] = np.nan
    return Zm
```

Any finite values whose absolute distance from the median is greater than  $k \times MAD$  are marked as outliers and are replaced with NaN. k is the outlier threshold, which has been set to 4. (A lower k is a stricter filter that would mask more data as outliers.) The function returns a copy of the input array with outliers replaced with NaN.